

How to use our V4 textures with Genesis 2 Female/V6 in Poser and DAZ Studio

What you'll need:

DAZ Studio users:

1. DAZ Studio 4.6 or newer
2. Victoria 4 or Genesis 1
3. V4 for Genesis 2 Female <http://www.daz3d.com/victoria-4-for-genesis-2-female>

Poser users:

1. DAZ Studio 4.6 or newer
2. Poser 9/ Pro 2012 or newer
3. Victoria 4 or Genesis 1
4. DSON Importer from <http://www.daz3d.com/dson-importer-for-poser>
5. V4 for Genesis 2 Female from <http://www.daz3d.com/victoria-4-for-genesis-2-female>
6. D3D's DSON Loader script from http://d3d.sessler.de/index.php?software=poserpython&product=dson_loader

What you need to do:

DAZ Studio users:

1. Load V4 or Genesis 1 in DAZ Studio
2. Load the material preset you want to use
3. Save the material preset as a DUF (File>Save As>Material(s) Preset) NOTE: Save inside a Materials preset library folder e.g. My Library\Presets\Materials\V4TexturesV6
4. Load Genesis 2 Female with Victoria 4 for Genesis 2 Female already installed
5. Load the DUF material preset saved in step 3.
6. Switch the UV Map to V4 (Surfaces Tab>Genesis 2 Female>UV Set>Victoria 4)
7. Save the material preset as DUF again as in step 3.
8. Close everything down and load DAZ Studio again to test
9. Load Genesis 2 Female with Victoria 4 for Genesis 2 Female already installed
10. Load the DUF material preset from step 7.

Poser users:

1. Load V4 or Genesis 1 in DAZ Studio
2. Load the material preset you want to use
3. Save the material preset as a DUF (File>Save As>Material(s) Preset) NOTE: Save inside a Materials preset library folder e.g. My Library\Presets\Materials\V4TexturesV6
4. Load Genesis 2 Female with Victoria 4 for Genesis 2 Female already installed
5. Load the DUF material preset saved in step 3.
6. Switch the UV Map to V4 (Surfaces Tab>Genesis 2 Female>UV Set>Victoria 4)

7. Save the material preset as DUF again as in step 3.
8. Close everything down and load DAZ Studio again to test
9. Load Genesis 2 Female with Victoria 4 for Genesis 2 Female already installed
10. Load the DUF material preset from step 7.
11. Load Poser
12. Load Genesis 2 Female with DSON Importer
13. Load the DSON Loader script from D3D
14. Navigate to the DUF file from step 7. and import it

You'll now need to spend some extra time setting up things like SSS, bump mapping etc. in Poser as you require.

If you have any questions about getting our textures to work with Genesis 2 Female/V6, just drop me a line at admin@most-digital-creations.com

I hope this information allows you to enjoy using V4 texture sets with Genesis 2 Female/V6.

Cheers

Adam

<http://www.most-digital-creations.com>